Package 'amapGeocode'

October 12, 2022

Type Package Title An Interface to the 'AutoNavi Maps' API Geocoding Services Version 0.6.0 Description Getting and parsing data of location geocode/reversegeocode and administrative regions from 'AutoNavi Maps'<https: //lbs.amap.com/api/webservice/summary> API. License MIT + file LICENSE **Depends** R (>= 3.5) Imports httr, jsonlite, magrittr, sjmisc, stats, xml2, data.table, furrr Suggests stringr, knitr, rmarkdown, testthat, spelling, covr VignetteBuilder knitr **Encoding** UTF-8 RoxygenNote 7.1.1 Language en-US URL https://github.com/womeimingzill/amapGeocode BugReports https://github.com/womeimingzi11/amapGeocode/issues NeedsCompilation no Author Han Chen [aut, cre], Wanyanhan Jiang [ctb] Maintainer Han Chen <chenhan28@gmail.com> **Repository** CRAN

Date/Publication 2021-04-19 07:20:02 UTC

R topics documented:

convertCoord								 							•				•		•			2
convertCoord.individual								 							•									3
extractAdmin	•	•	•	 •	•			 			•	•	•	•	•	•	•	•	•	•		•	•	4

convertCoord

extractConvertCoord		5
extractCoord		6
extractLocation		7
getAdmin		8
getAdmin.individual	1	0
getCoord	1	2
getCoord.individual	1	3
getLocation	1	5
getLocation.individual	1	7
num_coord_to_str_loc	1	9
str_loc_to_num_coord	1	9
	2	20

Index

convertCoord

Convert coordinate from different coordinate systems to AutoNavi system

Description

This function is a wrap of coordinate convert API of AutoNavi Map Service. While how to input the origin coordinate is sill unstable and 95% sure that it will have a breaking change in the future. Please consider carefully if introduced this function in product environment.

Usage

```
convertCoord(
  locations,
  key = NULL,
  coordsys = NULL,
  sig = NULL,
  output = "data.table",
  keep_bad_request = TRUE,
  ...
)
```

locations	Required. String coordinate point from other coordinate system
key	Optional. Amap Key. Applied from AutoNavi Map API official websitehttps://lbs.amap.com/dev/
coordsys	Optional. Coordinate System. Support: 'gps', 'mapbar', 'baidu' and 'autonavi'-not convert

sig	Optional. Digital Signature. How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72
output	Optional. Output Data Structure.
	Support JSON, XML and data.table. The default value is data.table.
keep_bad_reque	st
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request
	Optional. For compatibility only

Returns a JSON, XML or data.table of results containing detailed geocode information. See https: //lbs.amap.com/api/webservice/guide/api/convert for more information.

See Also

convertCoord

Examples

Not run: library(amapGeocode)

```
# Before the `convertCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `convertCoord()`
```

```
# get result of converted coordinate system as a data.table
convertCoord("116.481499,39.990475", coordsys = "gps")
# get result of converted coordinate system as a XML
convertCoord("116.481499,39.990475", coordsys = "gps", to_table = FALSE)
```

End(Not run)

convertCoord.individual

Convert an individual coordinate from different coordinate systems to AutoNavi system

Description

Convert an individual coordinate from different coordinate systems to AutoNavi system

Usage

```
convertCoord.individual(
  locations,
  key = NULL,
  coordsys = NULL,
  sig = NULL,
  output = "data.table",
  keep_bad_request = TRUE,
  ...
)
```

Arguments

locations	Required. String coordinate point from other coordinate system
key	Optional. Amap Key. Applied from AutoNavi Map API official websitehttps://lbs.amap.com/dev/
coordsys	Optional. Coordinate System. Support: 'gps', 'mapbar', 'baidu' and 'autonavi'-not convert
sig	Optional. Digital Signature. How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72
output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.
keep_bad_reque	st
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request
	Optional. For compatibility only

Value

Returns a JSON, XML or data.table of results containing detailed geocode information. See https: //lbs.amap.com/api/webservice/guide/api/convert for more information.

extractAdmin	Get Subordinate Administrative Region from getAdmin request Now, it only support extract the first layer of subordinate administrative region information.

extractConvertCoord

Description

Get Subordinate Administrative Region from getAdmin request Now, it only support extract the first layer of subordinate administrative region information.

Usage

```
extractAdmin(res)
```

Arguments

res Response from getAdmin.

Value

Returns a data.table which extracts detailed subordinate administrative region information from results of getCoord. See https://lbs.amap.com/api/webservice/guide/api/district for more information.

See Also

getAdmin

Examples

```
## Not run:
library(dplyr)
library(amapGeocode)
# Before the `getAdmin()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getAdmin()`
# Get subordinate administrative regions as a XML
getAdmin("Sichuan Province", output = "XML") %>%
# extract subordinate administrative regions as a data.table
extractAdmin()
## End(Not run)
```

extractConvertCoord Extract converted coordinate points from convertCoord request

Description

Extract converted coordinate points from convertCoord request

Usage

extractConvertCoord(res)

Arguments

res Required. Response from convertCoord.

Value

Returns a data.table which extracts converted coordinate points from request of convertCoord. See https://lbs.amap.com/api/webservice/guide/api/convert for more information.

See Also

convertCoord

Examples

```
## Not run:
library(dplyr)
library(amapGeocode)
# Before the `convertCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `convertCoord()`
# get result of converted coordinate system as a XML
convertCoord("116.481499,39.990475", coordsys = "gps", to_table = FALSE) %>%
# extract result of converted coordinate system as a data.table
extractConvertCoord()
## End(Not run)
```

extractCoord Extract coordinate from location request

Description

Extract coordinate from location request

Usage

```
extractCoord(res)
```

Arguments

res

Required. Response from getCoord.

extractLocation

Value

Returns a data.table which extracts detailed coordinate information from results of getCoord. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

getCoord

Examples

```
## Not run:
library(dplyr)
library(amapGeocode)
# Before the `getCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getCoord()`
# Get geocode as a XML
getCoord("IFS Chengdu", output = "XML") %>%
# extract geocode regions as a data.table
extractCoord()
```

End(Not run)

extractLocation Extract location from coordinate request

Description

Extract location from coordinate request

Usage

```
extractLocation(res)
```

Arguments

res	Required.
	Response from getLocation.

Value

Returns a data.table which extracts detailed location information from results of getLocation. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

getLocation

Examples

```
## Not run:
library(dplyr)
library(amapGeocode)
# Before the `getLocation()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getLocation()`
# Get reverse-geocode as a XML
getLocation(104.043284, 30.666864, output = "XML") %>%
    # extract reverse-geocode regions as a table
    extractLocation()
```

End(Not run)

```
getAdmin
```

Get Subordinate Administrative Regions from location

Description

Get Subordinate Administrative Regions from location

Usage

```
getAdmin(
   keywords,
   key = NULL,
   subdistrict = NULL,
   page = NULL,
   offset = NULL,
   extensions = NULL,
   filter = NULL,
   callback = NULL,
   output = "data.table",
   keep_bad_request = TRUE,
   ...
}
```

```
)
```

Arguments

keywords Required. Search keywords. Rules: Country/Region, Province/State, City, County/District, Town, Country, Road, Number, Room, Building.

getAdmin

key	Optional. Amap Key. Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/ dev/
subdistrict	Optional. Subordinate Administrative Level. Display level of subordinate administrative regions. Available value: 0,1,2,3. '0' do not return subordinate administrative regions. '1' return first one subordinate administrative regions. '2' return first two subordinate administrative regions. '3' return first three subordinate administrative regions.
page	Optional. Which page to return. Each time the outmost layer will return a maximum of 20 records. If the limit is exceeded, please request the next page of records with the page argument.
offset	Optional. Maximum records per page. Maximum value is 20.
extensions	Optional. Return results controller. 'base': does not return the coordinates of the administrative district boundary. 'all': returns only the boundary value of the current query district, not the bound- ary value of the child node.
filter	Optional. Filter administrative regions. Filtering by designated administrative divisions, which returns information only for the province/municipality. It is strongly recommended to fill in this parameter in order to ensure the correct records.
callback	Optional. Callback Function. The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.
output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.
keep_bad_reque	**
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request
	Optional. For compatibility only

Value

Returns a JSON or XML of results containing detailed subordinate administrative region information. See https://lbs.amap.com/api/webservice/guide/api/district for more information.

See Also

extractAdmin

Examples

Not run: library(amapGeocode) # Before the `getAdmin()` is executed, # the token should be set by `option(amap_key = 'key')` # or set by key argument in `getAdmin()` # Get subordinate administrative regions as a data.table getAdmin("Sichuan Province") # Get subordinate administrative regions as a XML getCoord("Sichuan Province", output = "XML") ## End(Not run)

getAdmin.individual Get an individual data.table of Subordinate Administrative Regions from location

Description

Get an individual data.table of Subordinate Administrative Regions from location

Usage

```
getAdmin.individual(
   keywords,
   key = NULL,
   subdistrict = NULL,
   page = NULL,
   offset = NULL,
   extensions = NULL,
   filter = NULL,
   callback = NULL,
   output = "data.table",
   keep_bad_request = TRUE,
   ...
)
```

keywords	Required. Search keywords. Rules: Country/Region, Province/State, City, County/District, Town, Country, Road, Number, Room, Building.
key	Optional. Amap Key. Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/ dev/
subdistrict	Optional. Subordinate Administrative Level. Display level of subordinate administrative regions. Available value: 0,1,2,3. '0' do not return subordinate administrative regions. '1' return first one subordinate administrative regions. '2' return first two subordinate administrative regions. '3' return first three subordinate administrative regions.
page	Optional. Which page to return. Each time the outmost layer will return a maximum of 20 records. If the limit is exceeded, please request the next page of records with the page argument.
offset	Optional. Maximum records per page. Maximum value is 20.
extensions	Optional. Return results controller. 'base': does not return the coordinates of the administrative district boundary. 'all': returns only the boundary value of the current query district, not the bound- ary value of the child node.
filter	Optional. Filter administrative regions. Filtering by designated administrative divisions, which returns information only for the province/municipality. It is strongly recommended to fill in this parameter in order to ensure the correct records.
callback	Optional. Callback Function. The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.
output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.
keep_bad_reque	st
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request

... Optional. For compatibility only

Value

Returns a JSON or XML of results containing detailed subordinate administrative region information. See https://lbs.amap.com/api/webservice/guide/api/district for more information.

getCoord

Get coordinate from location

Description

Get coordinate from location

Usage

```
getCoord(
  address,
  key = NULL,
  city = NULL,
  sig = NULL,
  output = "data.table",
  callback = NULL,
  keep_bad_request = TRUE,
  ...
)
```

address	Required. Structured address information. Rules: Country/Region, Province/State, City, County/District, Town, Country, Road, Number, Room, Building.
key	Optional. Amap Key. Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/ dev/
city	Optional. Specify the City. Support: city in Chinese, full pinyin, citycode, adcodehttps://lbs.amap. com/api/webservice/download. The default value is NULL which will search country-wide. The default value is NULL
sig	Optional. Digital Signature. How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72

output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.
callback	Optional. Callback Function. The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.
keep_bad_reque	st
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request
	Optional. For compatibility only

Returns a JSON, XML or data.table of results containing detailed geocode information. See https: //lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

extractCoord

Examples

```
## Not run:
library(amapGeocode)
# Before the `getCoord()` is executed,
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getCoord()`
# Get geocode as a data.table
getCoord("IFS Chengdu")
# Get geocode as a XML
getCoord("IFS Chengdu", output = "XML")
## End(Not run)
```

getCoord.individual Get an individual coordinate from location

Description

Get an individual coordinate from location

Usage

```
getCoord.individual(
  address,
  key = NULL,
  city = NULL,
  sig = NULL,
  output = "data.table",
  callback = NULL,
  keep_bad_request = TRUE,
  ...
)
```

Arguments

address	Required. Structured address information. Rules: Country/Region, Province/State, City, County/District, Town, Country, Road, Number, Room, Building.
key	Optional. Amap Key. Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/ dev/
city	Optional. Specify the City. Support: city in Chinese, full pinyin, citycode, adcodehttps://lbs.amap. com/api/webservice/download. The default value is NULL which will search country-wide. The default value is NULL
sig	Optional. Digital Signature. How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72
output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.
callback	Optional. Callback Function. The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.
keep_bad_reques	st
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request
	Optional. For compatibility only

getLocation

Value

Returns a JSON, XML or data.table of results containing detailed geocode information. See https: //lbs.amap.com/api/webservice/guide/api/georegeo for more information.

getLocation

Get location from coordinate

Description

Get location from coordinate

Usage

```
getLocation(
    lng,
    lat,
    key = NULL,
    poitype = NULL,
    radius = NULL,
    extensions = NULL,
    roadlevel = NULL,
    sig = NULL,
    output = "data.table",
    callback = NULL,
    homeorcorp = 0,
    keep_bad_request = TRUE,
    ...
)
```

lng	Required. Longitude in decimal
lat	Required. Latitude in decimal
key	Optional. Amap Key. Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/ dev/
poitype	Optional. Return nearby POI types. When 'extensions = all', this argument makes sense. For detailed poitype type, please referhttps://lbs.amap.com/api/webservice/download
radius	Optional. Searching radius. radius ranges from 0 to 3000, the default value is 1000, unit: meter.

extensions	Optional. Return results controller. 'base': the default value, it only return base information about coordinate. 'all': it will return nearby POI, road information and cross information.
roadlevel	Optional. Road levels. When 'extensions = all', this argument makes sense. 'roadlevel=0', return all roads. 'roadlevel=1', only return main roads.
sig	Optional. Digital Signature. How to use this argument? Please check here https://lbs.amap.com/faq/account/key/72
output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.
callback	Optional. Callback Function. The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.
homeorcorp	Optional. Optimize the order of returned POI or not. When 'extensions = all', this argument makes sense. 'homeorcorp=0', do not optimize, by default. 'homeorcorp=1', home related POIs are first, by default. 'homeorcorp=2', corporation related POIs are first, by default.
keep_bad_requ	est
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request
	Optional. For compatibility only

Returns a JSON, XML or data.table of results containing detailed reverse geocode information. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

See Also

extractCoord

Examples

Not run:
library(amapGeocode)

Before the `getLocation()` is executed,

getLocation.individual

```
# the token should be set by `option(amap_key = 'key')`
# or set by key argument in `getLocation()`
# Get reverse-geocode as a table
getLocation(104.043284, 30.666864)
# Get reverse-geocode as a XML
getLocation("104.043284, 30.666864", output = "XML")
## End(Not run)
```

getLocation.individual

Get an individual location from coordinate

Description

Get an individual location from coordinate

Usage

```
getLocation.individual(
    lng,
    lat,
    key = NULL,
    poitype = NULL,
    radius = NULL,
    extensions = NULL,
    roadlevel = NULL,
    sig = NULL,
    output = "data.table",
    callback = NULL,
    homeorcorp = 0,
    keep_bad_request = TRUE,
    ...
)
```

lng	Required. Longitude in decimal
lat	Required. Latitude in decimal
key	Optional. Amap Key. Applied from 'AutoNavi' Map API official websitehttps://lbs.amap.com/ dev/

poitype	Optional. Return nearby POI types. When 'extensions = all', this argument makes sense. For detailed poitype type, please referhttps://lbs.amap.com/api/webservice/download	
radius	Optional. Searching radius. radius ranges from 0 to 3000, the default value is 1000, unit: meter.	
extensions	Optional. Return results controller. 'base': the default value, it only return base information about coordinate. 'all': it will return nearby POI, road information and cross information.	
roadlevel	Optional. Road levels. When 'extensions = all', this argument makes sense. 'roadlevel=0', return all roads. 'roadlevel=1', only return main roads.	
sig	Optional. Digital Signature. How to use this argument? Please check herehttps://lbs.amap.com/faq/account/key/72	
output	Optional. Output Data Structure. Support JSON, XML and data.table. The default value is data.table.	
callback	Optional. Callback Function. The value of callback is the customized function. Only available with JSON output. If you don't understand, it means you don't need it, just like me.	
homeorcorp	Optional. Optimize the order of returned POI or not. When 'extensions = all', this argument makes sense. 'homeorcorp=0', do not optimize, by default. 'homeorcorp=1', home related POIs are first, by default. 'homeorcorp=2', corporation related POIs are first, by default.	
keep_bad_reque	est	
	Optional. Keep Bad Request to avoid breaking a workflow, especially meaningful in a batch request	
	Optional. For compatibility only	

Returns a JSON, XML or data.table of results containing detailed reverse geocode information. See https://lbs.amap.com/api/webservice/guide/api/georegeo for more information.

num_coord_to_str_loc Take longitude and latitude from location string out.

Description

Take longitude and latitude from location string out.

Usage

```
num_coord_to_str_loc(lng, lat)
```

Arguments

lng	Required.
	Longitude in decimal
lat	Required.
	Latitude in decimal

Value

Comma binded coordinate string

str_loc_to_num_coord Take longitude and latitude from location string out.

Description

Take longitude and latitude from location string out.

Usage

```
str_loc_to_num_coord(str_location)
```

Arguments

str_location Required. Location string from response

Value

vector contains Longitude and Latitude in numeric

Index

convertCoord, 2, 3, 6
convertCoord.individual, 3

extractAdmin, 4, *10* extractConvertCoord, 5 extractCoord, 6, *13*, *16* extractLocation, 7

getAdmin, 5, 8
getAdmin.individual, 10
getCoord, 7, 12
getCoord.individual, 13
getLocation, 8, 15
getLocation.individual, 17

 $\texttt{num_coord_to_str_loc, 19}$

str_loc_to_num_coord, 19